

Generating a PRN file for OptiEC printer.

- 1) Open up a DISCUS software.
- 2) Pick a desired CD size as shown on the fig. 1.




Fig.1 DISCUS software.

- 3) You should save all projects as a DISCUS file for future implementation. Go to **File => Save As...** type in a file name.




fig. 3 Save a project as a DISCUS file.

- 4) To generate a PRN file go to **File => Print...**
- 5) Highlight a **MF Digital OtiEC** printer and check the **Print to File** box as shown on a fig.2 then press **Print** button.




fig.2 Check the Print to file box

- 6) Type in a name for a PRN file. You can also specify the directory of the PRN file to be saved in.

NOTE:

You **MUST** use the **“.PRN”** extension to successfully generate a PRN file. See fig.4




fig. 4 Naming a PRN file. You must use the **“.PRN”** extension to successfully generate a PRN file.

- 7) You have successfully generated a PRN file.